



Windows 10 Driver Installation for GfG Drivers

1. Select the **“Start”** button.
2. Type **“startup”**.
3. Select **“Change advanced startup settings”**.
4. Select **“Restart now”** under the **“Advanced startup”** area.
5. Select **“Troubleshoot”**.
6. Select **“Advanced Options”**.
7. Select **“Startup Options”**.
8. Select **“Restart”**.
9. A menu will appear where you can press **“7”** on your keyboard to choose **“Disable driver signing enforcement”**.

Now Device Driver Signing should be disabled, allowing you to install any driver you like in Windows 10 until you reboot.

10. Now you can install the drivers normally, as with Windows 7 using the Device Manager to update the driver.

Note: this usually requires the drivers to be installed twice; once to install the USB device, and next to create a virtual COM Port.